

 RAND McNALLY

MileMaker[®] SP32

MILEMAKER[®]

LAN Installation Guide

MileMaker[®] SP32

MILEMAKER[®]

All features and functionality described in this document may not be included in the licensed software product. Please refer to your contract for details on the product licensed to you. Distance and other calculations referenced in this document are for illustrative purposes only; they may not reflect actual mileage. Information contained in this document is strictly confidential and proprietary to Rand McNally & Company. For use by authorized licensees only.

Copyright 2008 by Rand McNally & Company, MileMaker is a trademark of Rand McNally & Company. All other product names are trademarks of their respective holders.

LAN Installation Guide

© Rand McNally & Company
8255 North Central Park Avenue
Skokie, IL 60076-2970
Phone: (800) 234-4069
www.trucking.randmcnally.com

Table of Contents

- SYSTEM REQUIREMENTS 1**
 - Windows Standalone..... 1**
 - Local Area Network (LAN)..... 1**
- INSTALLATION INSTRUCTIONS 1**
 - Using the Setup Program..... 2**
 - LAN Installation 2**
- STARTING MILEMAKER SP32..... 3**

System Requirements

MileMaker SP32 can be installed as Windows standalone or a Local Area Network (LAN).

Windows Standalone

To run MileMaker SP32 on a Windows standalone system, you will need:

- Windows® XP SP2, Windows 2003 Server, Windows Vista Business.
- 32 MB of RAM.
- 265 MB of available hard drive space.
- CD Drive.

Local Area Network (LAN)

To run MileMaker SP32 on a LAN system, you will need:

- Windows Server® 2003, XP SP2, Windows 2003 Server, Windows Vista Business.
- 64 MB of RAM.
- 265 MB of available hard drive space.
- CD Drive.

Installation Instructions

MileMaker SP32 is supplied on a single CD-ROM. This CD is your master copy of MileMaker SP32, and should be stored in a safe place when not in use.

The setup program automatically installs the MileMaker SP32 applications and its associated files onto the hard disk of your computer. Before you can use MileMaker SP32, you must run the setup program.

Using the Setup Program

- ➔ To install MileMaker SP32:
 1. Insert the MileMaker SP32 CD-ROM into the CD drive.
 2. On the taskbar, click the **Start** button, and then click **Run**.
 3. In the **Run** dialog box, type **D:\Setup**, where **D:** represents the letter of your CD drive, and click **OK**.
 4. Follow the prompts on the screen to complete the installation.

LAN Installation

- ➔ To install the LAN version of MileMaker SP32:
 1. Install MileMaker SP32 on the LAN server by following the instructions in Using the Setup Program discussed above.
 2. On each client workstations, map the client to the server directory where you installed MileMaker SP32. Give the client write access to the MileMaker SP32 directory.
 3. Run the following install program from the server:
{mapped server drive}\{MileMaker SP32 path}\Client\Setup.exe
 4. When prompted for an MileMaker SP32 LAN User ID, type a unique user ID for the client workstation.
 5. Select the network drive and directory where LAN server was installed.
({mapped server drive}\{MileMaker SP32 path})

6. Follow the on the screen instructions. When prompted to **Choose Additional Files to Install**, select one of the options below:

Option	Space used	Explanation
No Additional Files	3 MB	Installs the minimum number of files on the client. This option saves space on the client workstation in return for slightly slower performance.
The Router Files	218 MB	Installs the Router files that are used for route calculation. This takes up additional disk space on the client but provides better performance.
The Map Files	25 MB	Installs the Map files used for the graphic display of maps. This takes up additional disk space on the client workstation but provides better performance.
Both Router and Map Files	240 MB	Installs both the Router and Map files. This takes the most disk space on the client workstation, but provides the best performance.

7. Repeat steps 2 through 6 for each client workstation running MileMaker SP32.

Starting MileMaker SP32

- ➡ To start MileMaker SP32:
1. Click the desktop icon.

